



How to Integrate Milesight's VS133-P Device into the Xenometric Platform



Version Change Log			
Version	Revision Date	Revision Details	Revised By
V1.0	20250421	Initial	Lockon



Preface

Xenometric is a professional platform focused on people counting and footfall analysis, widely used in scenarios such as retail, commercial complexes, transportation hubs, and public buildings. The platform can integrate data from a variety of sensors (such as thermal cameras, LiDAR, infrared devices, etc.) and uses intelligent algorithms to process and analyze this data in real-time. It provides key operational metrics such as footfall volume, entry/exit ratios, dwell time, and area heatmaps. Users can access historical data, generate visual reports, and conduct multi-dimensional trend analysis through Xenometric's web-based management interface or API, helping businesses optimize human resource allocation, space layout, and marketing strategies.

In terms of deployment, Xenometric offers a variety of flexible options to meet the needs of different types of customers. It can be installed on local enterprise servers (On-Premise), which is suitable for organizations with high data security requirements. It can also be deployed in private cloud environments owned by customers or via public cloud SaaS mode for quick deployment and zero maintenance. For scenarios that require both local control and cloud computing capabilities, a hybrid deployment model is supported. These diverse deployment options provide Xenometric with high adaptability and scalability in real-world implementations.

This document mainly demonstrates how to integrate the VS133-P device with the Xenometric SaaS platform, using dashboards and other examples.

1. Prerequisites

- **Sensor Model:** VS133-P
- **The device is connected to the Internet**

2. Account Registration

First, visit the [Footfall People Counting - Xenometric](#) interface:





Then click on “**CONTACT**”, and fill in your information on the redirected page:

Contact

Your Name (required)

Your Email (required)

Subject

Your Message

SEND

After receiving your information, Xenometric staff will create a username and password for you based on your requirements and send them to you via email.

3. Platform Parameter Retrieval

Normally, after the account is created, the platform will also provide you with a set of HTTP interface parameters based on your actual requirements.

The example below is for reference only, please refer to your own case:

Parameter	Description
URL Address	http://www.xenometric.com:6000
Timeout	Set as 30 seconds



Max Attempts	Set as 3
Max History	Set as 1000
Max Logs Post	Set as 100
Authentication	Token Leave blank
Authorization	Token Leave blank

4. Deployment Planning Parameters

First, determine how many buildings are involved in your deployment. Identify all zones in each building and assign a unique identifier to each (e.g., using uppercase letters and numbers).

Then, assign a unique identifier to each device (**Customized Site ID**).

For example, if you have only one VS133-P, you could name it **FLOOR4** like mine.

Next, configure a **Customized Device ID** for each device based on its function. You can temporarily set it as "AAAAAX" and send all parameters to the Xenometric staff. They will configure them on the platform and link them to your account using admin privileges. If you have any questions during this process, feel free to reach out to Xenometric for assistance.

Finally, Xenometric will provide you with an updated list based on your deployment plan, which includes building names, Site IDs, and Device IDs. This information is crucial for configuring the VS133-P and should not be modified arbitrarily in the future.

5. Terminal Device Configuration

First, follow the instructions in the [<VS133-P User Guide>](#) to connect the device to the Internet and co[VS133-P User Guide](#)ings such as time zone and system time.

Then, refer to the screenshot below to configure parameters for each VS133-P device. The fields **Customized Site ID**, **Customized Device ID**, and **Device Name** should be taken from Step 4.



Milesight

Dashboard
Rule
Communication
Report
Validation
System

English
admin

Device Info.

Device Name

People Counter

Product Model

VS133-P

SN

6757D16884840016

Hardware Version

V1.2

Software Version

V_133.1.0.8-12-12

MAC Address

24:E1:24:F7:4D:2D

Customized Device ID

[AAAAAX,ABABAX,ACACAX]

Customized Site ID

FLOOR4

Running Time

13 days 6 hours 30 minutes 57 seconds

Users

Username	User Level	Operation
admin	Administrator	
viewer	Viewer	

Current System Time

Date

11/03/2025

Time

16:24:40

Set the System Time

Time Zone

UTC+8:00 China Standard Time (CT/CST)

Daylight Saving Time

☐

Synchronize Time

Synchronize Mode

NTP Timing Manual Timing

Server Address

192.168.45.211

Time Interval

1 min(1-10000)

Milesight

Dashboard
Rule
Communication
Report
Validation
System

English
admin

TCP/IP

IP Assignment

Manual Automatic (DHCP)

IP Address

192.168.45.211

Subnet Mask

255.255.255.0

Default Gateway

192.168.45.1

Primary DNS Server

8.8.8.8

Secondary DNS Server

114.114.114.114

HTTPS

HTTPS

HTTPS Port

443

Certificate Installation Method

Create Self-Signed Certificate

Certificate

Enable

☐

Data Push Settings

Recipient Name

Xenometric

Report Protocol

HTTP(S)

URL

http://data.xenometric.com:6000

Connection Test

Test

Username

Password

Data Push Settings

Device Name	URL/Host	Protocol	Status	Operation
	http://data.xenom...	HTTP(S)	Disconnect	
	https://data.xemco...	HTTP(S)	Connected	
	192.168.45.8	HTTP(S)	Disconnect	
	http://192.168.60.8...	HTTP(S)	Connected	
	+Add			

6. Data Verification

Refer to the screenshot below to verify data upload:



Xenometric Reporting

Week by Day03/12/2025Milesight BuildingGo

PAGES

Visitors

Visitor Density

Live

Status

Dashboards

OPTIONS

Comparisons

Constraints

Locations

Favourites

SETTINGS

User Configuration

Download data

Previous Version

Reload

Logged in as: lockon.wen@milesight.com

Refresh

Status Report for Milesight Building

Site Name	Device Name	Site ID	Device ID	Last connection	Missing %	Counter Type	Physical ID	Serial	Link	Ext.
Milesight Building	FLOOR4-People Counter staff	FLOOR4	AC	12 Mar 2025 09:38:49	95.4%	Milesight	24E124F74D2D	6757D16884840016	103.84.136.171	

Copyright © Xenometric 2024Privacy PolicyTerms & ConditionsX-Server InstallX-Server No SQL ServerSwagger

Milesight

Dashboard

Rule

Communication

Report

Validation

System

English

admin

Line1

1

Total In

1

Total Out

0

Capacity

0

Staff In

0

Staff Out

0

Staff Capacity

0

Children In

0

Children Out

0

Children Capacity

Line2

0

Total In

1

Total Out

0

Capacity

0

Staff In

0

Staff Out

0

Staff Capacity

0

Children In

0

Children Out

0

Children Capacity

Region1

0

Total Count

0s

Max. Dwell

0s

Avg. Dwell

英语中文 (简体)

Google Translate

Video StreamStatic ImagesNo ImageColorGray

Xenometric Reporting

Week by Day03/12/2025Milesight BuildingGo

PAGES

Visitors

Visitor Density

Live

Status

Dashboards

OPTIONS

Comparisons

Constraints

Locations

Favourites

SETTINGS

User Configuration

Download data

Previous Version

Reload

Logged in as: lockon.wen@milesight.com


RefreshReset

Live Report for Milesight Building

Location	Visitors
Milesight Building	1
Milesight Building	1
Milesight Building Children	0
Milesight Building Staff	0
Milesight Building Visitors	1

Wednesday 12 March 2025 09:33:34

Copyright © Xenometric 2024Privacy PolicyTerms & ConditionsX-Server InstallX-Server No SQL ServerSwagger



At this point, the VS133-P device is successfully integrated with the Xenometric platform.

7. Frequently Asked Questions

Q1: Can the Device Name contain special characters?

A1: It is not recommended. Please use uppercase letters and spaces only.

Q2: How should the Device ID be formatted?

A2: The format depends on the rules you configure in the VS133-P. For detailed guidance, please consult [Xenometric staff](#) refer to Section 2.2 of the documentation.

-END-